[V8][V9] FAQ: How to determine the number of client licenses required before upgrading from AhsayOBS version 6 to AhsayCBS?

Article ID: 8038

Reviewed: 2019-03-27

Product Version:

Ahsay Software: 8.1 to 8.x Ahsay Software: 9.1 to 9.x

OS: All platforms

Description

The license model for AhsayCBS (v7+) has changed, client application usages are now calculated per device/installation basis, so if you are upgrading from version 6 to AhsayCBS, you will need to pay attention to the new license requirement.

This article describes the steps to determine the number of additional AhsayOBM / ACB licenses required before you perform the upgrade.

Steps

To determine the number of client licenses required, refer to the following steps:

- For installation on Windows:
 - 1. Download the license requirement calculator by Clicking Here.
 - 2. Extract the downloaded zip file to the AhsayOBS installation folder.
 - 3. In command prompt, browse to the "check" folder, for example:
 - 4. Execute the "ShowV7Usage.bat" batch file, for example:
 - 5. Open the output "usage.xml" file found within the same folder with a text editor (e.g. Notepad++).
 - 6. The current license usages and new license required will be displayed at the end of the file:

```
usage.xml
</User>
<ObmCountV6>103</ObmCountV6>
```

```
<AcbCountV6>14</AcbCountV6>
<ObmCountV7>126</ObmCountV7>
<AcbCountV7>14</AcbCountV7>
</Users>
```

From the above example:

ObmCountV6 = AhsayOBM licenses currently used in version 6 (e.g. 103) AcbCountV6 = AhsayACB licenses currently used in version 6 (e.g. 14)

ObmCountV7 = AhsayOBM licenses to be required in version 8 (e.g. 126) AcbCountV7 = AhsayACB licenses to be required in version 8 (e.g. 14)

You will need an additional of 23 AhsayOBM device licenses (e.g. 126 - 103 = 23) when upgrading from version 6 to 8.

Note:

Ignore the parameters' name reference to version 7 (e.g. ObmCountV7 and AcbCountV7), the license requirement for version 7 and 8 are identical. Also, the numbers used above are for example purposes only.

For installation on Linux:

- 1. Download the license requirement calculator by Clicking Here.
- 2. Extract the downloaded zip file to the AhsayOBS installation folder.
- 3. Browse to the "check" folder from the extracted file, for example:
- 4. Execute the "ShowV7Usage.sh" script file:
- 5. Open the output "usage.xml" file found within the same folder with a text editor.
- 6. The current license usages and new license required will be displayed at the end of the file:

```
...

</User>
</br>
</body>
</br>
</body>
<br/>
</br>
<br/>
</br>
<br/>
</br>
<br/>
</br>
<br/>
<
```

From the above example:

ObmCountV6 = AhsayOBM licenses currently used in version 6 (e.g. 103) AcbCountV6 = AhsayACB licenses currently used in version 6 (e.g. 14)

https://wiki-new.ahsay.com/ Printed on 2024/03/18 07:28

ObmCountV7 = AhsayOBM licenses to be required in version 8 (e.g. 126) AcbCountV7 = AhsayACB licenses to be required in version 8 (e.g. 14)

You will need an additional of 23 AhsayOBM device licenses (e.g. 126 - 103 = 23) when upgrading from version 6 to 8.

Note:

Ignore the parameters' name reference to version 7 (e.g. ObmCountV7 and AcbCountV7), the license requirement for version 7 and 8 are identical. Also, the numbers used above are for example purposes only.

For AhsayUBS:

- 1. Download the license requirement calculator by Clicking Here, or by running the 'fetch' command.
- 2. Extract the downloaded zip file to the AhsayOBS installation directory (e.g. /ubs/mnt/esfmfw/obsr/system/obsr)
- 3. Browse to the "check" folder from the extracted file, for example:
- 4. Execute the "ShowV7Usage.sh" script file:
- 5. Open the output "usage.xml" file found within the same folder with a text editor.
- 6. The current license usages and new license required will be displayed at the end of the file:

```
usage.xml
   </User>
   <ObmCountV6>103</ObmCountV6>
   <AcbCountV6>14</AcbCountV6>
   <ObmCountV7>126</ObmCountV7>
   <AcbCountV7>14</AcbCountV7>
</Users>
```

From the above example:

ObmCountV6 = AhsayOBM licenses currently used in version 6 (e.g. 103) AcbCountV6 = AhsayACB licenses currently used in version 6 (e.g. 14)

ObmCountV7 = AhsayOBM licenses to be required in version 8 (e.g. 126) AcbCountV7 = AhsayACB licenses to be required in version 8 (e.g. 14)

You will need an additional of 23 AhsayOBM device licenses (e.g. 126 - 103 = 23) when upgrading from version 6 to 8.

Note:

Ignore the parameters' name reference to version 7 (e.g. ObmCountV7 and AcbCountV7), the license requirement for version 7 and 8 are identical. Also, the numbers used above are for example purposes only.

Keywords

license, cal, cals, calculate, calculation, model, licensing, obm, acb, extra, more

From:

https://wiki-new.ahsay.com/ - Ahsay Wiki

Permanent link:

 $https://wiki-new.ahsay.com/doku.php?id=public:8038_faq:how_to_determine_client_lic_required_before_upgrade$

Last update: 2022/11/18 09:17

https://wiki-new.ahsay.com/ Printed on 2024/03/18 07:28